

**Exam Code:** HP0-242

**Exam Name:** Supporting the ESL9000

**Vendor:** HP

**Version:** DEMO

## Part: A

1: On which Operator Control Panel screen can you read error logs?

- A.Overview
- B.Tapes
- C.Operator
- D.Service

**Correct Answers: C**

2: The Use Barcodes button on the Systest Library screen of an ESL library is activated. What occurs?

- A.Selected cartridges are swapped during the test, based on the barcode label.
- B.Barcodes are read as cartridges are swapped.
- C.Cartridges are not swapped; barcodes are used to simulate cartridge swapping.
- D.Cartridges are returned to the previous location after the test terminates.

**Correct Answers: B**

3: What is the maximum number of times an HP Ultrium cleaning cartridge can be used?

- A.5
- B.10
- C.15
- D.20

**Correct Answers: C**

4: What is the format of the ESL Interface Manager Command Line Interface command prompt?

- A.CLI >
- B.<user>/<command\_level> >
- C.IM >
- D.<library name> >

**Correct Answers: B**

5: The Interface Manager card in an ESL library connects to the Fibre Channel Interface Controllers across a \_\_\_\_.

- A.PCI bus
- B.multimode Fibre Channel cable
- C.private Ethernet cable
- D.serial cable

**Correct Answers: C**

6: The Actions button on a Command View ESL screen is used to \_\_\_\_.

- A.perform the selected action
- B.open a menu of currently available actions
- C.display information about the current action
- D.take control over the current action

**Correct Answers: B**

7: From which Operator Control Panel screen can you configure library options?

- A.License
- B.Tapes
- C.Services
- D.Operator

**Correct Answers: D**

8: The cascade port of the Interface Manager card in an ESL library uses \_\_\_\_.

- A.DHCP by default to acquire an IP address across the network
- B.a pre-assigned, customizable IP address
- C.no IP address by default; you must set it during the configuration process
- D.a hardcoded IP address that cannot be changed

**Correct Answers: D**

9: What is the default baud rate for configuring the Fibre Channel interface card through the serial connection?

- A.9600
- B.19200
- C.57600
- D.115200

**Correct Answers: D**

10: Which connection type has the highest priority when connecting to a Network Storage Router (NSR) through the Interface Manager card?

- A.Command View ESL
- B.Telnet
- C.FTP
- D.Serial

**Correct Answers: D**

11: Which HP SDLT technology features are NOT provided in Ultrium? Select TWO.

- A.Adaptive Tape Speed
- B.linear recording
- C.pivoting optical servo
- D.cartridge memory
- E.DLT backward read compatibility

**Correct Answers: C E**

12: Which HP Ultrium technology features are NOT provided in SDLT? Select TWO.

- A.linear Recording
- B.DLT backward compatibility
- C.Adaptive Tape Speed

- D.pivoting optical servo
- E.cartridge memory

**Correct Answers: C E**

13: What is the maximum number of Ultrium-2 tape drives supported per SCSI port?

- A.1
- B.2
- C.3
- D.4

**Correct Answers: A**

14: Which different slot licenses does the ESL9595 support?

- A.200, 400, and 595
- B.100, 300, and 595
- C.400, 500, and 595
- D.326, 450, and 595

**Correct Answers: C**

15: Which document should you refer to when planning to install an ESL9000 library?

- A.ESL9000 Series Tape Library Maintenance and Service Guide
- B.ESL9000 Series Tape Library Pre-Installation Site Survey
- C.ESL9000 Series Tape Library User Guide
- D.ESL9000 Series Tape Library PTM Installation Guide

**Correct Answers: B**